

Scheduled recording function FCM-IP1 Software version 2.0 (2015-9-7)

The scheduled recording function is moved from the settings window to the multiview window (the icon with four squares). Click the camera you wish to set up recording on to select it, and then right-click on the camera picture.




You will see a menu with two options: *Scheduled recording setting* and *Configure save path*. Start with *Configure save path* and select where the files should be stored. Then right-click again and select *Scheduled recording setting* and add up to 8 schedules. Set them to *Enable* and select day(s) and time, and press the green checkmark next to *Saving recording settings?* at the bottom of the window.



IMPORTANT INFORMATION:

- The multiview window must be active. The program can be minimized or behind other windows as long as the multiview is active. If you go to the settings page or any other page, the recording won't work as the video stream is only running when the multiview window is active.
- Don't use special characters in the file path (åäö#%& and similar).
- The program can record from multiple cameras at the same time. This is also depending on the local network in order to get the data from the cameras to the PC.
- The recording will create one file per recording slot, so if it's many hours the file will be very big.

There is still a recording function present in the settings menu, but this is only covering one slot and records to the SD card (as before). This function is not changed.



You set the days and time you want to record to the SD card and then press save. Note that this does not allow recording over midnight unless you record all 24 hours.